# **Getting Started With EddyPro®**


Getting Started Guide

This document provides a broad overview of EddyPro Software work flows. EddyPro is tightly integrated with the LI-COR eddy covariance system—the simplest way to use EddyPro is with the LI-7500A, LI-7200, or GHG systems that include the LI-7700. However, you can process virtually any type of dataset with EddyPro, including ASCII, binary, TOB1, and SLT files.


Processing LI-COR GHG Files in Express Mode	1
Processing LI-COR GHG Files in Advanced Mode	2
Processing ASCII, Binary, TOB1 or SLT Files in	
Express Mode	3
Processing ASCII, Binary, TOB1 or SLT Files in	
Advanced Mode	4

## **Processing LI-COR GHG Files in Express Mode**


1. Create a New Project.



- Enter the Project Name.
- (Optional) If site parameters that change over time are not addressed in the metadata files, create a Dynamic Parameters File.
- (Optional) Select Biomet data to use data collected from other sensors.



2. Set the Raw Data Directory.



- Enter the Output Directory and Output ID.
- (Optional) Select items for flux computation.
- Configure flag thresholds and policies.
- 3. Click Run in Express Mode.




4. View Results.

Flux results are in the file named eddypro\_"Output ID"\_full\_output\_YYYY-MM-DDTHHMMSS.




## **Processing LI-COR GHG Files in Advanced Mode**

1. Create a New Project.




- Enter the Project Name.
- (Optional) If site parameters that change over time are not addressed in the metadata files, create a Dynamic Parameters File.
- (Optional) Select Biomet data to use data collected from other sensors.
- 2. Set the Raw Data Directory.




- Enter the Output Directory and Output ID.
- (Optional) Select items for flux computation.
- Configure flag thresholds and policies.

### 3. Configure Advanced Settings.



- Processing Options
- Spectral Corrections
- Statistical Analysis
- Output Files
- 4. Click Run in Advanced Mode.



### 5. View Results.


Flux results are in the file named eddypro\_"Output ID"\_full\_output\_YYYY-MM-DDTHHMMSS.

## **Processing ASCII, Binary, TOB1 or SLT Files in Express Mode**


1. Create a New Project.




- Enter the Project Name.
- (Optional) If site parameters that change over time are not addressed in the metadata files, create a Dynamic Parameters File.
- (Optional) Select Biomet data to use data collected from other sensors.
- 2. Create a New or Load an Existing Metadata File.



- Select the Raw File Format.
- Enter station and instrument information.
- Enter the raw file description and settings.
- Or, load a metadata file from a previous project.
- 3. Set the Raw Data Directory.



- Enter the Output Directory and Output ID.
- (Optional) Select items for flux computation.
- Configure flag thresholds and policies.
- 4. Click Run in Express Mode.



5. View Results.

Flux results are in the file named eddypro\_"Output ID"\_full\_output\_YYYY-MM-DDTHHMMSS.

### Processing ASCII, Binary, TOB1 or SLT Files in Advanced Mode

1. Create a New Project.




- Enter the Project Name.
- (Optional) If site parameters that change over time are not addressed in the metadata files, create a Dynamic Parameters File.
- (Optional) Select Biomet data to use data collected from other sensors.
- 2. Create a New or Load an Existing Metadata File.




- Select the Raw File Format.
- Enter station and instrument information.
- Enter the raw file description and settings.
- Or, load a metadata file from a previous project.


#### 3. Set the Raw Data Directory.



- Enter the Output Directory and Output ID.
- (Optional) Select items for flux computation.
- Configure flag thresholds and policies.
- 4. Configure Advanced Settings.



- Processing Options
- Spectral Corrections
- Statistical Analysis
- Output Files
- 5. Click Run in Advanced Mode.



6. View Results.

Flux results are in the file named eddypro\_"Output ID" full output YYYY-MM-DDTHHMMSS.



### LI-COR Biosciences Global Headquarters

4647 Superior Street Lincoln, Nebraska 68504

Phone: +1-402-467-3576 • Toll free: 800-447-3576 • Fax: +1-402-467-2819 envsales@licor.com • envsupport@licor.com • www.licor.com/env

### Regional Offices

### LI-COR GmbH, Germany

Serving Andorra, Albania, Belarus, Cyprus, Estonia, Germany, Iceland, Latvia, Lithuania, Liechtenstein, Malta, Moldova, Monaco, San Marino, Ukraine, and Vatican City.
LI-COR Biosciences GmbH

Siemensstraße 25A

61352 Bad Homburg

Germany

Phone: +49 (0) 6172 17 17 771 • Fax: +49 (0) 6172 17 17 799 envsales-gmbh@licor.com • envsupport-gmbh@licor.com

LI-COR Ltd., United Kingdom

Serving Denmark, Finland, Ireland, Norway, Sweden, and UK. LI-COR Biosciences UK Ltd. St. John's Innovation Centre

Cowley Road

Cambridge

CB4 0WS

United Kinadom

Phone: +44 (0) 1223 422102 • Fax: +44 (0) 1223 422105

envsales-UK@licor.com • envsupport-UK@licor.com

#### LI-COR Distributor Network:

www.licor.com/env/distributors

© LI-COR, Inc. 2015

07/15 977-12756